

Basics of Soybean Fertility

Soil and Plant Testing

Managing soybean fertility should begin with regular soil testing. Soil testing is a valuable and inexpensive tool for ascertaining the nutrient and pH status of a particular field and guiding field input decisions. Soil tests should be taken every three to four years and sent to a reputable lab for analysis.

Standard soil tests generally measure pH, buffer pH (or lime test index, which is buffer pH x10), available phosphorus (P), exchangeable potassium (K), calcium (Ca), magnesium (Mg), cation exchange capacity (CEC) and organic matter (OM). Note that soil test values may be reported in either pounds per acre (lb/acre) or parts per million (ppm). To convert ppm into lb/acre, multiply ppm by 2.

Micronutrient soil tests will report amounts of the other nutrients (at a greater cost), but these quantities do not always correlate well with nutrient application recommendations in agronomic crops. Tissue testing in-season is recommended for identifying and confirming micronutrient deficiencies indicated by soil tests.

When diagnosing a suspected in-season nutrient deficiency, take soil and tissue samples from a normal area of the field in addition to the affected area. Comparing these reports will give additional insight into possible nutrient issues and increased confidence in diagnosis and confirmation of a deficiency.

Soil pH

The pH of a soil is a measure of the acidity or concentration of hydrogen ions in the soil solution. Many chemical and biological processes in the soil are affected by pH, and maintaining pH in the proper range will maximize the efficiency of other crop inputs and decrease the risk of yield losses. Soybeans thrive in the pH range of 6.0 to 6.8 (in mineral soils). Figure 1 shows the availability of essential nutrients as a function of soil pH.




Figure 1. Relative availability of plant nutrients by soil pH.

Most of these nutrients are more available within than beyond this optimal pH range. Note also that some nutrients become less available as pH rises above 6.8, so “blanket” applica-

tions of lime above this point may be detrimental to the crops. Another reason for keeping pH in the desired range is to support beneficial microorganism activity in the soil, particularly *Bradyrhizobium japonicum*, which is responsible for fixing nitrogen in soybean root nodules.

Nitrogen (N)

Soybean is a high-protein crop and requires a large quantity of nitrogen (N) to synthesize amino acids and proteins. As a legume crop, however, soybeans supply most of their own N needs by fixation of atmospheric N_2 into ammonium (NH_4^+), a form that is readily available to the plant. Additional N is scavenged from the soil through organic matter cycling and rainfall deposition to supply N needs not met by nodulation.

Research has shown that if ammonium or nitrate is available to be absorbed from the soil when nodules are present, N-fixation will decrease proportionally. For this reason, N fertilization in soybeans rarely results in agronomic or economic yield increases when nodulation is normal, and is generally not recommended. However, research in some irrigated, high-yield environments has demonstrated that N applied during the pod or seed stages of soybean development may increase yield.

Phosphorus (P) and Potassium (K)

Phosphorus (P) and potassium (K) are macronutrients, or nutrients that are needed in relatively large quantities compared to others. The content of both P and K in soybeans is high relative to that of corn and wheat on a per bu basis. A 60 bu/acre soybean crop would remove about 48 lbs P_2O_5 and 84 lbs K_2O from the soil in the grain. By comparison, a 200 bu/acre corn crop would remove more P (74 lbs P_2O_5) and less K (54 lbs K_2O).

Soil testing should be used to determine the levels of plant-available P and K. These nutrients must be in high enough quantities in the soil to prevent plant deficiencies, but once this critical level is reached, additional yield gains with higher levels of P and K are generally not realized. University studies put the critical level for P in the range of 30 to 40 pounds per acre. The critical level of K is more variable at about 90 to 150 lbs/acre, depending on the CEC of the soil.

Symptoms of K deficiency include yellowing of the margins of the leaves, starting with the older, lower leaves. Note the yellowing pattern beginning at the leaf margins in Figure 2.



Figure 2. Potassium deficiency in soybeans. Photo courtesy of Robert Mullen, Ohio State University.

Phosphorus deficiency symptoms include stunting, spindly stems and dark-green to bluish coloration of plant tissue. Fertilizing on a crop-removal basis with P and K can be a good agronomic practice once the critical levels are reached. In research studies, banding P and K usually does not produce consistently better yield results than broadcast applications. Fertilizers should not be placed with the soybean seed due to risk of seedling injury and stand loss from salt-induced stresses associated with fertilizers.

Sulfur (S) and Magnesium (Mg)

Sulfur (S) is an important plant nutrient that is available in the soil from cycling of organic matter and atmospheric deposition. Sandy, low organic matter soils are associated with S deficiencies. Also, atmospheric deposition of sulfate in the eastern Corn Belt and northeast is typically higher than in the Great Plains and Midwestern states due to the operation of coal-fired power plants. Soybeans with S deficiencies will exhibit pale green-yellow color in topmost leaves.

Soybeans require 20 to 25 pounds of S per year, and in cases of high organic matter soils or manured fields, a high percentage is derived from the soil. Ammonium sulfate, ammonium thiosulfate, gypsum, potassium sulfate, magnesium sulfate and elemental sulfur are potential sources of supplemental S.

Magnesium (Mg) deficiencies are relatively uncommon, but may occur in areas of acidic, sandy soils. Interveinal chlorosis and mottling will occur on deficient plants, starting with the lower (older) leaves. These areas may appear bronzed or speckled as the deficiency progresses.

Magnesium is usually reported in standard soil test and tissue test reports. The critical level for exchangeable Mg in the soil is 50 ppm or 100 lb/acre. The simplest method for supplementing soil Mg is by the use of dolomitic limestone, magnesium sulfate or potassium magnesium sulfate. In some cases, excessive K in the soil can hinder the plant's ability to take up Mg.

Micronutrients

Compared to the macronutrients, micronutrients are equally necessary for plant growth and yield, albeit in smaller quantities. Since only small amounts are required, there is a narrow margin between "sufficient" and "toxic" rates for some micronutrients.

Highly productive soils usually contain sufficient micronutrients for optimum crop growth, but specific soil environments or features and weather patterns can result in deficiencies. Soil pH adjustments may increase micronutrient availability in some cases, though some deficiencies are induced by other factors, such as organic matter and texture.

Manganese (Mn) – One of the more common micronutrient deficiencies observed in soybeans is manganese (Mn), which is most likely to occur in coarse, dry, high pH and high organic matter soils. Manganese deficiency symptoms include interveinal chlorosis on the newest (topmost) leaves while the



Figure 3. Manganese-deficient soybean plants. (Photo courtesy of Ron Gehl, North Carolina State University).

veins remain green (Figure 3). Manganese is fairly immobile in the plant, rendering symptoms on the newest soybean leaves.

Consistent field history of Mn deficiencies may guide the decision-making for a soil-applied Mn amendment, but foliar applications are also appropriate for treatment with a Mn product. Test soybean tissue (20 topmost trifoliolate leaves with stems or petioles removed) to confirm Mn deficiency before application. Research reports that less than 21 ppm in the tissue indicates low Mn, and crop response may result from foliar Mn treatment from growth stage V6 to R1.

Iron (Fe) – Iron deficiency chlorosis (IDC) symptoms are similar to those of manganese, with interveinal chlorosis and severe stunting, and are usually associated with native high pH soils. This condition is yield-limiting in many soybean fields in the northern and western U.S. Primary management practices include variety selection, iron chelate treatments and increased soybean seeding rates.



Variety Selection – Because soybean varieties vary widely for tolerance to IDC, variety selection is the first and most important step in managing this problem. Pioneer Hi-Bred has a significant research effort to screen its soybean varieties in areas with IDC. This effort allows Pioneer to rate existing varieties as well as identify new varieties that can help growers overcome yield losses to IDC. Pioneer® brand varieties are rated on a one to nine scale where one indicates poor tolerance and nine indicates excellent tolerance. If growers are planting into an area with a history of IDC, they should select varieties with an IDC score of six, seven or eight.